
1.Make Folder for the Project e.g. Pioneer_Control

2.Copy all files from this folder to Pioneer_Control




Path for files-

C:\Program

 $Files \verb|\Coppel| ia SimEdu \verb|\programming \verb|\legacyRemoteApi| remote Api Bindings \verb|\python \verb|\python| python | python$

3.Copy this file into Pioneer_Control (It has files for MacOs and Ubuntu) select according to OS.




Path for file-


Windows

C:\Program

 $Files \label{legacyRemoteApi} In the legacy Remote Api \label{lib} Windows$



- 4.Open CoppeliaSim. Save First Scene eg. First_test in the folder Pioneer_Control.
- 5. Add child lua script to the any object in the scene. Eg. To the Floor.



6. Open that script and paste following for the connection.

simRemoteApi.start(19999)

```
**Child script "/Floor"

**D** **A** **E** **E** **Independent of the property of the property
```

7. Write Code in python (eg. First_test_code) and save it in the same folder (eg. Pioneer_Control).

Following code provides connection between python and CoppeliaSim

sim.simxStart('127.0.0.1', 19999, True, True, 5000, 5)

```
import sim
import sys

print("Program Started")
sim.simxFinish(-1) # just in case, close all opened connections
clientID = sim.simxStart('127.0.0.1', 19999, True, True, 5000, 5)# Connect to CoppeliaSim

if(clientID != -1):
    print('Connected Successfully.')
else:
    sys.exit('Failed To connect.')
```

Complete code-

import sim


import sys

print("Program Started")

sim.simxFinish(-1)

```
clientID = sim.simxStart('127.0.0.1', 19999, True, True, 5000, 5)
if(clientID != -1):
    print('Connected Successfully.')
else:
    sys.exit('Failed To connect.')
```

8. Run the Simulation in the Coppelia Sim



9.Run the Python script

C:\Users\saura\OneDrive\Desktop\Pioneer_Control>python First_test_code.py
Program Started
Connected Successfully.


Example to Run basic code and control Pioneer 3DX in the CoppeliaSim using python.

10.Example script to run the Pioneer robot.

I have added scene "Pioneer_control" and the script "Control_robot.py" for your reference.



Before running this script Disable the original Pioneer script in the CoppeliaSim



Code-

import sim

import time

import sys

print("Program Started")

sim.simxFinish(-1) #CLose the previous connection

```
clientID = sim.simxStart('127.0.0.1', 19999, True, True, 5000, 5) # Establish the connection
if(clientID != -1):
  print('Connected Successfully.')
else:
  sys.exit('Failed To connect.')
time.sleep(1)
#Get the object handle for the motors
error_code, left_motor_handle = sim.simxGetObjectHandle(clientID, '/PioneerP3DX/leftMotor',
sim.simx_opmode_oneshot_wait)
error_code, right_motor_handle = sim.simxGetObjectHandle(clientID, '/PioneerP3DX/rightMotor',
sim.simx_opmode_oneshot_wait)
#Give the commands to the robot about velocity
error_code = sim.simxSetJointTargetVelocity(clientID, left_motor_handle, 0.4,
sim.simx_opmode_oneshot_wait)
error_code = sim.simxSetJointTargetVelocity(clientID, right_motor_handle, 1,
sim.simx_opmode_oneshot_wait)
```

Script explanation

Import Sim

```
import sim
import time
import sys

print("Program Started")
sim.simxFinish(-1) #CLose the previous connection
clientID = sim.simxStart('127.0.0.1', 19999, True, True, 5000, 5) # Establish the connection


if(clientID != -1):
    print('Connected Successfully.')
else:
    sys.exit('Failed To connect.')

time.sleep(1)
```

Get object handle eg. right motor



Set velocity



Documentation Link

https://manual.coppeliarobotics.com/en/remoteApiFunctionsPython.htm

simxSetJointTargetVelocity

	Sets the intrinsic target velocity of a non-spherical joint. This command makes only sense when the joint mode is in torque/force mode: the dynamics functionality and the joint motor have to be enabled (position control should however be disabled)
Python synopsis	number returnCode=simx <mark>SetJointTargetVelocity</mark> (number clientID,number jointHandle,number targetVelocity,number operationMode)
,	clientID: the client ID. refer to simxStart. jointHandle: handle of the joint targetVelocity: target velocity of the joint (linear or angular velocity depending on the joint-type) operationMode: a remote API function operation mode. Recommended operation modes for this function are simx_opmode_oneshot or simx_opmode_streaming
Python return values	returnCode: a remote API function return code
Other languages	C/C++, Java, Matlab, Octave